
FILE CONVERSIONS Importing and Exporting Files

Converting the Census Bureau Pipe Delimited File to Other Formats (Importing Files)

Key Terms

- What is "Pipe Delimited"?
 - "Pipe" is located on the keyboard directly above the "enter/return" key, by pressing the shift key.



 "Delimited" is what separates the data in a line of text into columns in a spreadsheet. Some types of "Delimiters" are commas, spaces, asterisks, and for LUCA it's "Pipe".


Converting Pipe Delimited into Other Formats For Example: Text Editors, Access, Excel

Text Editors:

- Pipe Delimited files will read directly into Text Editors.
- Depending on your computer,
 - you may be able to double click on the file to open it; or
 - you may need to right click on the file and select "Open As..." and select Text, Notepad or Wordpad.

Converting Pipe Delimited into Other Formats For Example: Text Editors, Access, Excel


- Access Database Format
 - Open Access, using file open, navigate to the address list. A wizard should pop-up after you select the list.
 - On the first screen, specify "Delimited" as the format and click "Next".




Access Database Format Continued

 In the next screen, for the delimiter, click "Other" and type in "|", then click next.






 In the following wizard, change all the field's to "Text", by clicking on the column and selecting "Text" for each column. Click "Finish".



Converting Pipe Delimited into Other Formats For Example: Text Editors, Access, Excel

- Excel Spreadsheet Format:
 - Steps are very similar to Access
 - Open Excel.
 - Navigate to the Address List (you may need to view all files by selecting the file drop-down at the bottom of the screen).




- Select the Address list and click "Open".

Excel Spreadsheet Format Continued

- A wizard should pop-up. Just as in Access, select "Delimited" as the data type, click "Next".
- Just as in Access, specify the Delimiter as "Other" and type in "|", click "Next".
- On the third screen, change all fields to "Text" This is critical for the data to read correctly. Click on each column and select "Text" as the "Column data format". You will need to do this for EVERY COLUMN. Click finished when done.
- Note: Excel can only handle 65,536 rows of data. If you have more addresses than this, you will need to work within another software package or work with multiple spreadsheets.

Excel Spreadsheet Format Continued



Submitting Local Address List as a Pipe Delimited File (Exporting Files)

2010 Census LUCA Training Workshop Census Bureau's Predefined Computer-readable Format

	Maximum Character Length	Field Name	Description/Notes						
1	12	Entity ID Code	Unique number assigned by the Census Bureau to each entity						
2	2	State Code	2-digit Current State Code						
3	3	County Code	3-digit Current County Code						
4	7	Census Tract Number	Up to 4-digit Census Tract Number, plus 2-digit number suffix, if applicable, includes a period for suffixed tracts. If no suffix, include period and zero fill						
5	5	Census Block Number	4-digit Current Census Block Number, plus 1-digit alpha character suffix if applicable						
6	1	Group Quarters Flag	Display a 'Y' if the unit is a group quarters, if applicable						
7	35	House Number	Housing unit's or group quarter's assigned house number						
8	3	Street Name Prefix Qualifier	e.g. EXT, ALT, BUS						
9	2	Street Name Prefix Direction	e.g., N, W, SE						
10	14	Street Name Prefix Type	e.g., HWY, RT, US						
11	100	Street Name	Street or road name						
12	14	Street Name Suffix Type	e.g., ST, CT, AVE, DR						
13	2	Street Name Suffix Direction	e.g., N,W, SE						
14	3	Street Name Suffix Qualifier	e.g. EXT, ALT, BUS						
15	100	Group Quarters Name	Name of group quarter (Dobbs Hall-University of Dobbs)						
16	53	Apartment/Unit Number	Within structure descriptor or identifier, such as APT 5 or 1st FL FRNT						
17	5	Mailing ZIP Code	5-digit ZIP Code for mailing addresses						

Format conversions to Pipe Delimited

- You can convert directly from a Text Editor or Access into Pipe Delimited.
- Conversions from Text Editors:
 - Open the file in a text editor
 - To replace the delimiter with pipes:
 - Go to: Edit, Select "Replace"
 - Copy the delimiter (if it is "tab" will look like a blank space) and paste it into the "Find what" field
 - Type | in the "Replace with" field
 - Select "Replace All"

Converting from Another Delimited Format to Pipe Delimited


Open file in a text editor. Use "Find and Replace".

copy_tab_test.txt - Notepad													□ x	
Enity I St Pref St Suff 88008 13612	D Code ix Qual ix Qual 88	State C ifier ifier 8	St Pref	County Fix Direc Quarters 2021	tion	Census Tract St Name Prefi Apartment/Uni 2825	x Type	St Name	Block Nu e St Sufi g Zip Coo Maple	fix TV:	GQ Flag Ho pe St Suffix	use Number Direction		
88008 13612	88	8	9404	2021		2827	W		Maple	ST	Copy the t	ab		
88008	88	8	9404	2021		2831	W		Maple	ST	oopy me t	u.		
13612 88008	88	8	9404	2021		2831 1/2		W		марТе	e ST			
H 88008	13612 88	8	9404	2021		2841	W		Maple	ST				
13612 88008	8		9404	2021		2839	W		Maple	ST				
13612 88008	88	8	9404	2021		2835	W		Maple	ST	Posto in t	the Find fie		
13612 88008	88	8	9404	2021		1823	N		Elm	ST		ine Fina ne	;IU	
13612 88008	88	8	9404	2021		1827	N		Elm	ST				
13612 88008	88	8	9404	2021		1831	N		Elm /	ST	Renlace	with a " "		
13612 88008	88	8	9404	2021		1835	N		ĘŽm	ST	/ Kepiace	with a		
13612 88008	88	8	9404	2021		1839	Replace				?×			
13612 88008	88	8	9404	2021		1843					Find Next			
13612 88008	88	8	9404	2021		2824	Find what:							
13612 88008	88	8	9404	2021		2832	Replace with:				Replace			
13612 88008	88	8	9404	2021		2840					Replace All			
13612 88008	88	8	9404	2015		4640	☐ Match ca	se			Cancel			
Apt 337 88008		8	9404	2015		4640								
Apt 338		8	9404	2015		4640			Roge	LN				
Apt 339		8	9404	2015		4640			Rose	LN				
Apt 340 88008 Dormito	13612 88	8	9404 9404 13612	2013	Υ	1420 Click "	'Replac	e All"	Rose	AVE		Lamar	▼	

USCENSUSBUREAU

For tab delimited, highlight the space between columns Copy and paste in the "Find what:" field.

Converting from Another Delimited Format to Pipe Delimited




Format conversions to Pipe Delimited

- Access database files
 - Export as a delimited text file using the wizard setup:
 - Go to File "Export..."
 - In "Save as type" select "Text Files (*.txt;*cvs;*.tab, *asc)
 - Click "Save All"
 - Select "Delimited" in the Export Wizard
 - Click "Next"
 - Click the delimiter as "Other" and type in |
 - In "Text Qualifier" click "{None}" and then "Next"
 - Type in the location to export to
 - Click Finish

Converting from Access Database Format to Pipe Delimited

Open file in Access. Select "Export" in the file menu and save as a text delimited file.




USCENSUSBUREAU

Choose other as delimiter and enter "|" into the field. Select the text qualifier as "none".

Converting from Access Database Format to Pipe Delimited

Export to file using the naming convention.



USCENSUSBUREAU


Use your entity identification code as part of the file name XXyyyyyyy_LUAL.txt

Format conversions to Pipe Delimited

- Excel spreadsheet files
 - You can not convert directly into Pipe Delimited from Excel
 - You will first need to convert the file to "Text (Tab delimited) (*.txt)" or "CSV (Comma delimited) (*.csv)" and then use text editor to convert the file to Pipe Delimited (see previous slides for Text Editor conversions)
 - To convert to "Text":
 - Open the Excel file
 - Select "File" then "Save as..."
 - Under "Save as type:" scroll down and select either CSV (Comma delimited) or Text (Tab delimited"
 - Select "Save"

Converting from Excel Spreadsheet Format to Pipe Delimited

Open file in Excel. Select "Save As". Choose either a tab or cvs delimited text file.



USCENSUSBUREAU

Follow steps for converting delimiter text files.